

# CONFIGURATION WITH NEW CONFIGURATION SOFTWARE

## RECONFIGURATION EXTENDER TO STANDALONE eMH3 TWIN

|   |   |
|---|---|
| 1 | Press [Individual Configuration] button                                 |
| 2 | Switch on charging station  |
| 3 | Wait 15 seconds   |
| 4 | Press [Scan] button   |
| 5 | Press radiobutton to switch to standalone mode                          |
| 6 | Deselect checkmark at Advanced Configuration to apply the configuration |